

rowshape() — Reshape matrix

Description
Diagnostics

Syntax
Also see

Remarks and examples

Conformability

Description

`rowshape(T, r)` returns *T* transformed into a matrix with `trunc(r)` rows.

`colshape(T, c)` returns *T* having `trunc(c)` columns.

In both cases, elements are assigned sequentially with the column index varying more rapidly. See [M-5] `vec()` for a function that varies the row index more rapidly.

Syntax

transmorphic matrix `rowshape(transmorphic matrix T, real scalar r)`

transmorphic matrix `colshape(transmorphic matrix T, real scalar c)`

Remarks and examples

stata.com

Remarks are presented under the following headings:

Example of rowshape()

Example of colshape()

Example of rowshape()

```

: A
      1   2   3   4
1   11  12  13  14
2   21  22  23  24
3   31  32  33  34
4   41  42  43  44

: rowshape(A,2)
      1   2   3   4   5   6   7   8
1   11  12  13  14  21  22  23  24
2   31  32  33  34  41  42  43  44

```

Example of `colshape()`

```
: colshape(A, 2)
      1      2
```

1	11	12
2	13	14
3	21	22
4	23	24
5	31	32
6	33	34
7	41	42
8	43	44

Conformability

`rowshape(T, r)`:

T : $r_0 \times c_0$
 r : 1×1
result: $r \times r_0 c_0 / r$

`colshape(T, c)`:

T : $r_0 \times c_0$
 c : 1×1
result: $r_0 c_0 / c \times c$

Diagnostics

Let r_0 and c_0 be the number of rows and columns of T .

`rowshape()` aborts with error if $r_0 \times c_0$ is not evenly divisible by `trunc(r)`.

`colshape()` aborts with error if $r_0 \times c_0$ is not evenly divisible by `trunc(c)`.

Also see

[M-4] [manipulation](#) — Matrix manipulation