

xtnbreg postestimation — Postestimation tools for xtnbreg

Description
Methods and formulas

Syntax for predict
Also see

Menu for predict

Options for predict

Description

The following postestimation commands are available after `xtnbreg`:

Command	Description
<code>contrast</code>	contrasts and ANOVA-style joint tests of estimates
<code>estat ic</code> ¹	Akaike's and Schwarz's Bayesian information criteria (AIC and BIC)
<code>estat summarize</code>	summary statistics for the estimation sample
<code>estat vce</code>	variance–covariance matrix of the estimators (VCE)
<code>estimates</code>	cataloging estimation results
<code>forecast</code> ²	dynamic forecasts and simulations
<code>hausman</code>	Hausman's specification test
<code>lincom</code>	point estimates, standard errors, testing, and inference for linear combinations of coefficients
<code>lrtest</code>	likelihood-ratio test
<code>margins</code>	marginal means, predictive margins, marginal effects, and average marginal effects
<code>marginsplot</code>	graph the results from margins (profile plots, interaction plots, etc.)
<code>nlcom</code>	point estimates, standard errors, testing, and inference for nonlinear combinations of coefficients
<code>predict</code>	predictions, residuals, influence statistics, and other diagnostic measures
<code>predictnl</code>	point estimates, standard errors, testing, and inference for generalized predictions
<code>pwcompare</code>	pairwise comparisons of estimates
<code>test</code>	Wald tests of simple and composite linear hypotheses
<code>testnl</code>	Wald tests of nonlinear hypotheses

¹ `estat ic` is not appropriate after `xtnbreg, pa`.

² `forecast` is not appropriate with `mi` estimation results.

Syntax for predict

Random-effects (RE) and conditional fixed-effects (FE) overdispersion models

`predict [type] newvar [if] [in] [, RE/FE_statistic nooffset]`

Population-averaged (PA) model

`predict [type] newvar [if] [in] [, PA_statistic nooffset]`

<i>RE/FE_statistic</i>	Description
Main	
xb	linear prediction; the default
stdp	standard error of the linear prediction
nu0	predicted number of events; assumes fixed or random effect is zero
iru0	predicted incidence rate; assumes fixed or random effect is zero
pr0(<i>n</i>)	probability $\Pr(y_j = n)$ assuming the random effect is zero; only allowed after <code>xtnbreg, re</code>
pr0(<i>a,b</i>)	probability $\Pr(a \leq y_j \leq b)$ assuming the random effect is zero; only allowed after <code>xtnbreg, re</code>
PA_statistic	
mu	predicted number of events; considers the <code>offset()</code> ; the default
rate	predicted number of events
xb	linear prediction
stdp	standard error of the linear prediction
score	first derivative of the log likelihood with respect to $\mathbf{x}_j\beta$

These statistics are available both in and out of sample; type `predict ... if e(sample) ...` if wanted only for the estimation sample.

Menu for predict

Statistics > Postestimation > Predictions, residuals, etc.

Options for predict

Main

- xb** calculates the linear prediction. This is the default for the random-effects and fixed-effects models.
- mu** and **rate** both calculate the predicted number of events. **mu** takes into account the `offset()`, and **rate** ignores those adjustments. **mu** and **rate** are equivalent if you did not specify `offset()`. **mu** is the default for the population-averaged model.
- stdp** calculates the standard error of the linear prediction.
- nu0** calculates the predicted number of events, assuming a zero random or fixed effect.
- iru0** calculates the predicted incidence rate, assuming a zero random or fixed effect.
- pr0(*n*)** calculates the probability $\Pr(y_j = n)$ assuming the random effect is zero, where *n* is a nonnegative integer that may be specified as a number or a variable (only allowed after `xtnbreg, re`).
- pr0(*a,b*)** calculates the probability $\Pr(a \leq y_j \leq b)$ assuming the random effect is zero, where *a* and *b* are nonnegative integers that may be specified as numbers or variables (only allowed after `xtnbreg, re`);

b missing ($b \geq .$) means $+\infty$;

`pr0(20,.)` calculates $\Pr(y_j \geq 20)$;

`pr0(20, b)` calculates $\Pr(y_j \geq 20)$ in observations for which $b \geq .$ and calculates $\Pr(20 \leq y_j \leq b)$ elsewhere.

`pr0(., b)` produces a syntax error. A missing value in an observation on the variable a causes a missing value in that observation for `pr0(a , b)`.

`score` calculates the equation-level score, $u_j = \partial \ln L_j(\mathbf{x}_j\beta) / \partial(\mathbf{x}_j\beta)$.

`nooffset` is relevant only if you specified `offset(varname)` for `xtnbreg`. It modifies the calculations made by `predict` so that they ignore the offset variable; the linear prediction is treated as $\mathbf{x}_{it}\beta$ rather than $\mathbf{x}_{it}\beta + \text{offset}_{it}$.

Methods and formulas

The probabilities calculated using the `pr0(n)` option are the probability $\Pr(y_{it} = n)$ for a RE model assuming the random effect is zero. A negative binomial model is an overdispersed Poisson model, and the nominal overdispersion can be calculated as $\delta = s/(r - 1)$, where r and s are as given in the estimation results. Define $\mu_{it} = \exp(\mathbf{x}_{it}\beta + \text{offset}_{it})$. Then the probabilities in `pr0(n)` are calculated as the probability that $y_{it} = n$, where y_{it} has a negative binomial distribution with mean $\delta\mu_{it}$ and variance $\delta(1 + \delta)\mu_{it}$.

Also see

[XT] **xtnbreg** — Fixed-effects, random-effects, & population-averaged negative binomial models

[U] **20 Estimation and postestimation commands**